


HOE KAN IK MIJN BASIC MAILBOX CONFIGUREREN IN WINDOWS LIVE MAIL (IMAP)?

1. Open Windows Live Mail.



2. Wissel naar het tabblad Accounts en klik op E-mail. Stel uw mail als volgt in:

A screenshot of the 'Add your email accounts' dialog box in Windows Live Mail. The dialog box has a red title bar and a blue header. The main content area is white with a light blue gradient background. It contains the following text and fields:

Add your email accounts
If you have a Windows Live ID, sign in now. If not, you can create one later.
[Sign in to Windows Live](#)

Email address:

[Get a Windows Live email address](#)

Password:

 Remember this password

Display name for your sent messages:


Manually configure server settings

Most email accounts work with Windows Live Mail including
Hotmail
Gmail
and many others.

Cancel Next

1. Vul uw e-mail adres in.
2. Vul uw e-mail wachtwoord in en vink Dit wachtwoord onthouden aan.
3. Toon de instellingen.
4. Vink aan: Serverinstellingen manueel invullen.
5. Klik op Volgende.

3. Configureer de instellingen van uw server:



Configure server settings
 If you don't know your email server settings, contact your ISP or network administrator.

Incoming server information

Server type:

Server address: Port:

Requires a secure connection (SSL)

Authenticate using:

Logon user name:

Outgoing server information

Server address: Port:

Requires a secure connection (SSL)

Requires authentication

Cancel Back Next

1. Kies bij server type voor IMAP.

IMAP:

imap.mailprotect.be

(poort: 143; SSL poort: 993)

2. Kopieer het adres van de inkomende mailserver vanuit uw My Combell

3. Vink aan: Beveiligde verbinding vereist (SSL)

4. Selecteer 'Clear text'

5. Vul uw e-mail adres in als Login gebruikersnaam.

6. Kopieer het e-mail adres van uw uitgaande server vanuit uw My Combell

SMTP:


smtp-auth.mailprotect.be

(poort: 2525; SSL poort: 465)

7. Vink aan: Beveiligde verbinding vereist (SSL)

8. Vink aan: Vereist Authenticatie

9. Klik op Volgende



The screenshot shows the 'Configure server settings' dialog box in Windows Live Mail. The window title is 'Windows Live Mail'. The main heading is 'Configure server settings' with a subtitle: 'If you don't know your email server settings, contact your ISP or network administrator.' The dialog is divided into two columns: 'Incoming server information' and 'Outgoing server information'. In the 'Incoming' section, 'Server type' is set to 'IMAP', 'Server address' is 'imap.mailprotect.be', 'Port' is '993', and 'Requires a secure connection (SSL)' is checked. 'Authenticate using' is set to 'Clear text'. The 'Logon user name' is 'user1@uwdomeinnaam.be'. In the 'Outgoing' section, 'Server address' is 'smtp-auth.mailprotect.be', 'Port' is '465', and both 'Requires a secure connection (SSL)' and 'Requires authentication' are checked. At the bottom right, there are three buttons: 'Cancel', 'Back', and 'Next'.

4. Klik op Voltoeien